

# Sadevio Cloud System Connector

To connect your on-premise access control system, you can install the SADEVIO Cloud Connector service. This service facilitates the integration of the SADEVIO Cloud Solution with your access control system.

## Overview

[Screenshot 2024-06-27 at 2.56.46 PM.png](#)

Download the Sadevio Cloud Connector and install it in the same network, where the Velocity Server is.

## Configure Sadevio Cloud System.

- **Create a New Access System:**
  - Navigate to the **Maintenance** section.
  - Select **Access System**.
  - Click on **Create New Access System**.
- **Set Connector Type:**
  - Select **Web Socket** as the access system connector type.
  - This action will generate an application ID.
- **Record Application ID:**
  - Make a note of the generated application ID, as it will be needed for configuring the Cloud Connector.

[image.png](#)

## Configure Sadevio Cloud Connector

- **Locate the Configuration File:**
  - The configuration file for the Sadevio Cloud Connector is named `appsettings.json`.
  - You can find it in the `ProgramData` directory, usually located at `C:\ProgramData\Sadevio`.
- **Open the Configuration File:**
  - Navigate to the `C:\ProgramData\Sadevio` directory.

- Open the `appsettings.json` file with a text editor.
- **Activate the Cloud Connector Function:**
  - In the `appsettings.json` file, ensure that the cloud connector function is activated and the application id set.

[Screenshot 2024-06-27 at 3.13.03 PM.png](#)

## Configure Identiv Velocity features

1. **Locate the Configuration Section:**
  - In the `appsettings.json` file, find the configuration section for the access system.
2. **Set Access System Type:**
  - Set the `access_system_type` to `velocity_rest`.
3. **Enter Connection Details:**
  - Provide the IP address of your Velocity system.
  - Enter the generated password. See [Generate API Password](#)

Example configuration in `appsettings.json`:

[Screenshot 2024-06-27 at 5.36.27 PM.png](#)

## Configure Velocity Badge Template

- **Open Velocity Client:**
  - Launch your Velocity Client application.
- **Navigate to Credential Template Configuration:**
  - Go to **Configuration**.
  - Select **Velocity Configuration**.
  - Click on **Credential Template**.
- **Create a New Credential Template:**
  - Add the required functions as needed.
  - Press **OK** to save the new credential template.

[Screenshot 2024-06-27 at 3.19.33 PM.png](#)

### Retrieve and Configure Template ID:

- Note the template ID of the newly created credential template.
- Open the `appsettings.json` file.
- Set the `velocity_rest_template_id` to the template ID. For example, set it to `30`.

[Screenshot 2024-06-27 at 3.20.30 PM.png](#)

## Configure Velocity Card Format

The card format configuration is used to determine which algorithm is used to generate the Velocity MATCH Code. Refer to the [Velocity Card Format Mapping](#) section in our documentation for details on the available algorithms.

To use "Special 36" for generating the MATCH CODE, follow these steps:

**1. Locate the Configuration Section:**

- In the `appsettings.json` file, find the configuration section for card format.

**2. Set the Card Format:**

- Configure the `velocity_rest_card_format` variable to the appropriate value. For "Special 36," set it to `41`.

---

Revision #7

Created 27 June 2024 21:46:47 by Admin

Updated 28 June 2024 00:43:56 by Admin